



U.S. Department  
of Transportation  
Federal Aviation  
Administration

# Aviation Environmental Design Tool (AEDT)

Version 2d Service Pack 2

Installation Guide

September 2019



## Table of Contents

1	Installation Introduction .....	3
2	Technical Assistance .....	3
3	System Requirements .....	4
3.1	Note for International Users .....	5
3.1.1	SQL Server Collation .....	5
3.1.2	Windows Region and Language .....	5
3.2	Upgrading from SQL Server 2008 R2 to SQL Server 2012 .....	6
3.2.1	Option 1. Use the Migrate Studies Feature in AEDT 2d B Recommended .....	6
3.2.2	Option 2. In-Place Upgrade of SQL Server 2008 R2 Instance to SQL Server 2012 .....	6
4	Installation Package Contents .....	8
4.1	Microsoft SQL Server Software .....	8
4.2	AEDT Software .....	8
5	Software Installation .....	8
5.1	Typical Installation Configurations .....	8
5.2	Install Microsoft SQL Server 2012 .....	9
5.3	Install AEDT 2d SP2 .....	20
5.3.1	Install AEDT 2d SP2 .....	20
5.3.2	Migrate User-Defined AEDT Study Databases .....	29
5.3.3	Upgrade User-Defined AEDT Study Databases .....	29
5.4	Optional – Install AEDT Distributed Processing Service .....	30
5.4.1	Setup AEDT Client .....	32
5.4.2	Setup Taskmaster Servers Running Distributed Processing Service .....	32
5.5	Manage AEDT Databases .....	38
5.5.1	Verify AEDT System Database Versions .....	38
5.5.2	Backup SQL Server Database .....	38
5.5.3	Restore SQL Server Database .....	39
5.5.4	Delete SQL Server Database .....	40
5.6	Steps to Uninstall AEDT .....	42

### 1 Installation Introduction

This document provides detailed instructions on how to install and run AEDT 2d Service Pack 2 (SP2). It is important to follow the installation instructions in the order listed below, as Microsoft SQL Server 2012 is a prerequisite for AEDT. Installation components must run locally.

1. Install Microsoft SQL Server 2012
2. Install AEDT 2d SP2



To install software, the user must have administrative rights to the computer.

### 2 Technical Assistance

The AEDT Support website, <https://aedt.faa.gov/>, is the technical support hub for AEDT. Support requests, feedback on bugs, and feature requests should be submitted through this website. The AEDT installer and support resources such as documentation and frequently asked questions (FAQ) are also available on the AEDT Support website. Register on the website to request support or submit feedback on AEDT. Additional options for support include:

- E-mail: [aedt-support@dot.gov](mailto:aedt-support@dot.gov)
- Phone: 617-494-2603

Please include the AEDT Administrative File when requesting technical support. Please refer to Section 4.11.2 in the AEDT User Guide for instructions on generating the Administrative File.

### 3 System Requirements

System specifications for computers capable of hosting the AEDT 2d application are displayed in Table 3-1. The preferred specifications are listed with suggested minimum requirements where applicable.

Table 3-1 AEDT 2d System Requirements

	AEDT 2d System Specifications		
	Minimum	Preferred	For Running Global Level Studies
<b>Operating Systems<sup>1</sup></b>	Microsoft Windows 7 (x64)	Microsoft Windows 7 (x64) or Window Server 2012	Microsoft Windows 7 (x64) or Windows Server 2012
<b>Processor</b>	Modern dual core processor with 2 GHz or higher clock	Modern many core (>2) processors with 2 GHz or higher clock	Modern many core (>2) processors with 2 GHz or higher clock
<b>RAM</b>	8 GB	16 GB	64 GB
<b>Hard Disk Space</b>	100 GB Storage	500 GB Storage	2 TB Storage RAID
<b>Microsoft SQL Server</b>	SQL Server 2012 Express	SQL Server 2012	SQL Server 2012
<b>Other Software</b>	Adobe Reader X (v10) or higher	Adobe Reader X (v10) or higher	Adobe Reader X (v10) or higher



The supported Microsoft SQL Server version for AEDT 2d is Microsoft SQL Server 2012. The support for Microsoft SQL Server 2008 R2 ended with the AEDT 2d release.



AEDT requires administrative privileges for both 1) installation and 2) execution of the software.



AEDT uses the accelerated map display that is part of the ArcGIS Runtime SDK for WPF in order to achieve performance benefits when displaying map layers. Accelerated display is disabled if the computer's graphics hardware does not meet requirements or when accessing AEDT remotely (e.g. through Remote Desktop). When accelerated display is disabled, map layers may require additional time to load.

<sup>1</sup> Use Windows Update to ensure your computer has the latest priority updates.



The recommended screen resolution is 1920x1080.



It is recommend to include AEDT application as an exception to antivirus run time scan.

### 3.1 Note for International Users

#### 3.1.1 SQL Server Collation

During the SQL Server installation, select **SQL\_Latin1\_General\_CP1\_CI\_AS**. Upgrading an older AEDT study database to the latest study version will fail if different collation is used, see Section 5.2.

#### 3.1.2 Windows Region and Language

AEDT supports only **“English (United States)”** format for the Windows Region and Language.

*To change Windows Region and Language:*

1. Open the Windows Control Panel.
2. Click *Region and Language*.
3. In the *Region and Language* dialog box, select **“English (United States)”** as the *Format*.
4. Click OK to save your changes and close the dialog box.




Figure 3-1 Windows Region and Language Dialog Box

## 3.2 Upgrading from SQL Server 2008 R2 to SQL Server 2012

This section is applicable to users who have been using older AEDT versions with SQL Server 2008 R2. Skip this section if you are a new user or have already migrated to SQL Server 2012.

With the AEDT 2d release, the support for Microsoft SQL Server 2008 R2 ended; and SQL Server 2012 is the only supported SQL Server version. Therefore, existing AEDT study databases on a SQL Server 2008 R2 instance must be migrated to a new SQL Server 2012 instance, if you wish to use them in AEDT 2d.

This section explains two options for upgrading from SQL Server 2008 R2 to SQL Server 2012. Both options assume that SQL Server 2008 R2 (v10.5) is currently used with the existing AEDT installation (e.g. AEDT 2c).

### 3.2.1 Option 1. Use the Migrate Studies Feature in AEDT 2d **β Recommended**

The *Migrate Studies* feature in AEDT 2d application supports copying studies on a SQL Server 2008 R2 instance to a SQL Server 2012 instance. Using this option is recommended.

#### *To migrate by using the Migrate Studies feature in AEDT 2d:*

1. Install SQL Server 2012 side-by-side with 2008 R2. This will create a SQL Server 2012 instance.
2. Install AEDT 2d.
  - During AEDT installation, select the SQL Server 2012 instance (created from the previous step).
3. Use the *Migrate Studies* feature in the AEDT 2d application (refer to the instructions in the AEDT User Guide).
4. After migration, upgrade AEDT user-defined studies to the most current AEDT study version, see Section 5.3.3.
  - This will copy the AEDT study databases in a 2008 R2 instance to a 2012 instance.
  - You can choose which studies in the 2008 R2 instance to migrate to a 2012 instance.
  - AEDT study databases in the 2008 R2 instance are not removed or replaced.

### 3.2.2 Option 2. In-Place Upgrade of SQL Server 2008 R2 Instance to SQL Server 2012

This option uses the in-place upgrade feature of the Microsoft SQL Server Installation wizard. The feature allows users to upgrade instances of SQL Server 2008 R2 to SQL Server 2012. All the databases (including any AEDT databases) on the selected SQL Server 2008 R2 instance will be upgraded to SQL Server 2012 version.



When you upgrade SQL Server, the previous SQL Server instance (i.e. 2008 R2) will be overwritten and will no longer exist on your computer. Before upgrading, back up SQL Server databases and other objects associated with the previous SQL Server instance.



If you have a Standard/Developer/Enterprise edition of 2008 R2, use the SQL Server 2012 Installer that is same as or higher than the 2008 R2 edition.

For example, a SQL Server 2008 R2 *Standard* edition cannot be upgraded to 2012 using a SQL Server 2012 *Express* Installer. It must be upgraded using a SQL Server 2012 Standard or higher edition installer.

# Aviation Environmental Design Tool

## Installation Guide: 2d SP2

---

### *To upgrade to SQL Server 2012 by using the SQL Server Installation Wizard:*

1. Run the SQL Server 2012 Installer.
2. Click the *Upgrade from SQL Server 2005, SQL Server 2008 or SQL Server 2008 R2* option.
3. Follow the SQL Server Setup instructions to upgrade a SQL Server 2008 R2 instance to 2012.




Figure 3-2 SQL Server 2012 Installation Center

5. Make sure to select the correct SQL Server 2008 R2 instance that you want to upgrade to 2012.
6. After the SQL Server upgrade is complete, upgrade AEDT user-defined studies to the most current AEDT study version, see Section 5.3.3.

## 4 Installation Package Contents

### 4.1 Microsoft SQL Server Software

- **SQL\_Server\_2012\_SQLEXPRT\_x64\_ENU.exe** – Installer for Microsoft SQL Server 2012 Express and SQL Server Management Studio Express for 64-bit operating systems



The SQL Server Express (a free edition of SQL Server) has the following limitations:

- Limited to the lesser of one socket or four cores
- Maximum memory for the database engine is 1 GB
- Maximum database size is 10 GB per database

### 4.2 AEDT Software

- **Install AEDT 2d SP2.exe** – Installer for AEDT 2d SP2 application
- **Install AEDT 2d SP2 Distributed Processing.exe** – Installer for AEDT 2d SP2 Distributed Processing service (see Section 5.4)

## 5 Software Installation

This section contains installation instructions for Microsoft SQL Server 2012, AEDT, and Distributed Processing Service. Instructions for verifying the AEDT database versions and steps to uninstall AEDT are also included.

### 5.1 Typical Installation Configurations

There are two typical installation configurations for AEDT.

- **Standalone configuration:** The AEDT GUI application and AEDT databases are all installed on one machine. For this setup, first install Microsoft SQL Server (Section 5.2), then the AEDT application (Section 5.3).
- **Client – Server configuration:** The AEDT GUI application is installed on one or more client (individual) machines and connect to a separate database server where AEDT databases are installed. For this setup:
  - 1) On a SQL Server, install the AEDT application.
  - 2) On a client machine, first install the SQL Server then the AEDT application.
  - 3) Repeat step 2 for additional client machine as needed.



For Client – Server configuration, it is recommended to install the full AEDT (both application and databases) on the database server. It is useful to have the AEDT application on the database server for troubleshooting.



Accessing the same study database simultaneously by more than one user is not recommended.

In addition to the typical installation configurations, a distributed processing configuration can be setup to run metric results across a number of remote servers to reduce processing time, see Section 5.4.

### 5.2 Install Microsoft SQL Server 2012



The supported Microsoft SQL Server version for AEDT 2d is Microsoft SQL Server 2012.

The support for Microsoft SQL Server 2008 R2 ended with the AEDT 2d release.

**Microsoft SQL Server 2012 must be installed prior to installing AEDT 2d.** Please see Section 3.2 on options for migrating/upgrading from SQL Server 2008 R2 to SQL Server 2012.

The Express Edition installer for Microsoft SQL Server 2012 is included in the AEDT installation package (see Section 4). Instructions on installing the SQL Server 2012 Express Edition are described below. The steps and options may be different for other SQL Server Editions.



Microsoft SQL Server Management Studio (SSMS) Express is also installed as part of the installation. SQL Server Management Studio is a graphical management tool that allows for configuration and management of Microsoft SQL Server, including backing up and restoring databases and running SQL queries.

#### *To install Microsoft SQL Server 2012 Express Edition:*

1. Double-click the *SQL\_Server\_2012\_SQLEXPRT\_x64\_ENU.exe*.
2. Click *Run* if prompted to *Run* or *Cancel*.
3. The *SQL Server Installation Center* window will automatically launch when the files have finished extracting.
4. Click the *Installation* link on the left side of the window.
5. Click the appropriate installation option. Click the *New installation or add features to an existing installation* option unless upgrading from an older version.



Figure 5-1 SQL Server Installation Center – Installation Menu

6. SQL Server 2012 Setup will automatically run *Setup Support Rules* which will identify potential installation issues.

7. *License Terms*: Read the terms and check the box that reads *I accept the license terms*. Click *Next*.




Figure 5-2 SQL Server 2012 Setup – License Terms

8. *Product Updates*: Check the box to include the SQL Server product updates. Click *Next*.




Figure 5-3 SQL Server 2012 Setup – Product Updates

9. SQL Server 2012 Setup will automatically run *Install Setup Files*.

10. *Feature Selection*: The list of features will be different depending on the SQL Server Edition. Select the following features (additional features are optional). Click *Next*.

- *Database Engine Services*
  - *SQL Server Replication*
  - *Full-Text and Semantic Extractions for Search*
- *Management Tools – Basic*




Figure 5-4 SQL Server 2012 Setup – Feature Selection

11. *Instance Configuration*: When installing the Express Edition, the “Named instance” option is selected by default. Select the desired instance option. If *Named instance* is selected, change the named instance name as needed. Click *Next*.




Figure 5-5 SQL Server 2012 Setup – Instance Configuration



The SQL Server instance selected in this step should also be selected when installing AEDT (see Figure 5-19). For example, if “Default instance” is selected in this step, select the “(local)” instance when installing AEDT. If “Named instance” is selected, select the “(local)\[named instance]” when installing AEDT.

12. *Server Configuration*: In the *Service Account* tab, the default settings work in most cases. Change the settings if necessary.




Figure 5-6 SQL Server 2012 Setup – Server Configuration, Service Accounts Tab

13. *Server Configuration*: Click the *Collation* tab and confirm that “SQL\_Latin1\_General\_CP1\_CI\_AS” is selected. Click *Next*.



The default collation may be different for international users.

**SQL\_Latin1\_General\_CP1\_CI\_AS** must be selected or upgrading an older AEDT study database to the latest study version will fail.




Figure 5-7 SQL Server 2012 Setup – Server Configuration, Collation tab

14. *Database Engine Configuration*: Select the desired authentication mode. Click *Next*.




Figure 5-8 SQL Server 2012 Setup – Database Engine Configuration

15. *Error Reporting*: It is not necessary to select any of the options. Click *Next*.

16. *Installation Progress*: The progress bar and status will update until the installation is complete.




Figure 5-9 SQL Server 2012 Setup – Installation Progress

17. *Complete*: The final screen will confirm that the installation was successful. Click *Close* to close the *Setup* window.




Figure 5-10 SQL Server 2012 Setup – Complete

18. Close the *SQL Server Installation Center* window by clicking the *X* in the top right corner.

### 5.3 Install AEDT 2d SP2

Follow the instructions below to install AEDT 2d SP2. To install the AEDT application, the user must have administrative rights to the computer.



What is side-by-side installation?

Side-by-side installation is supported starting with AEDT 2c SP2.

AEDT can be installed side by side with an older AEDT release (e.g., 2c SP1, 2c, 2b SP3). The AEDT databases from two different versions can be installed on the same database server, but on two separate SQL Server instances. Create a new SQL Server instance before proceeding with side-by-side installation of AEDT.

Side-by-side installation supports installing newer AEDT version when an older AEDT version is already installed. It does not support installing an older AEDT on top of newer AEDT version.

#### 5.3.1 Install AEDT 2d SP2



Microsoft SQL Server 2012 must be installed prior to installing AEDT 2d SP2.

*To install AEDT 2d SP2 application and databases:*

1. To start the installer, double-click the *Install AEDT 2d SP2.exe* file.
2. If the *User Account Control* dialog box appears, click *Yes*.




Figure 5-11 User Account Control Dialog Box

# Aviation Environmental Design Tool

## Installation Guide: 2d SP2

---

3. The setup wizard for AEDT will open. The following software is required to install AEDT. If they are not already installed, the setup wizard will initiate installation of the required software.
- Microsoft .NET Framework 4.6.1
  - Microsoft Visual C++ 2010 SP2 Redistributable Package (x86)
  - Microsoft Visual C++ 2008 SP2 Redistributable Package (x64)
  - Microsoft Visual C++ Redistributable for Visual Studio 2015 Update 3 (x64)

Accept the license agreements and click *Install* to install the required software.

4. The setup wizard will display the welcome screen. Click *Next*.



Figure 5-12 AEDT Setup Wizard – Welcome

5. Read the license terms and click *I accept the terms of the license agreement*. Click *Next*.




Figure 5-13 AEDT Setup Wizard – License Agreement

# Aviation Environmental Design Tool

## Installation Guide: 2d SP2

---

6. If an older AEDT version is already installed, the following screen will be displayed (Figure 5-14).
  - Click *Yes* to remove the existing version and install AEDT 2d SP2. The same settings of the existing AEDT version will be used for AEDT 2d SP2 (SQL Server instance, installation folder, and data folder).
  - Click *No* to install AEDT 2d SP2 alongside with older AEDT version.

Click *Next* to continue.



**If SQL Server 2008 R2 was used with the existing AEDT version, do not click *Yes* in this step.** Click *Cancel* to stop the AEDT 2d SP2 installation, uninstall the existing AEDT version, then restart the AEDT 2d SP2 installation. During AEDT 2d SP2 installation, select a SQL Server 2012 instance.



This screen is not displayed if an AEDT versions older than 2c SP1 is already installed (e.g., 2c or 2b SP3). Side-by-side installation can be still performed by selecting a different SQL Server instance in subsequent step.




Figure 5-14 AEDT Setup Wizard – Upgrade Older Versions

7. Select the *Custom* setup type.

- *Complete*: installs all the AEDT components to default locations
- *Custom*: allows users to customize which AEDT component(s) to install and change the locations where the software is installed



The default installation locations are:

- AEDT installation folder – C:\Program Files\FAA\AEDT
- AEDT data folder – C:\AEDT

If there are files in the default locations at the time of installation, new folders will be created and named based on the AEDT version.

To customize the installation locations, choose the *Custom* option.




Figure 5-15 AEDT Setup Wizard – Setup Type

# Aviation Environmental Design Tool

## Installation Guide: 2d SP2

8. Select the features to install. If you are unsure what to select, leave all the features checked. Click *Next* to continue.




Figure 5-16 AEDT Setup Wizard – Custom Setup

9. Select the folder where AEDT will be installed. Click *Next* to continue.




Figure 5-17 AEDT Setup Wizard – Installation Folder

10. Select the data folder. Click *Next* to continue.



**Please make sure to specify a folder path without any spaces.**  
For example, change C:\AEDT 2d SP2 to C:\AEDT2dSP2




Figure 5-18 AEDT Setup Wizard – Data Folder

11. Select the desired database server instance from the drop-down menu or type the name of the server in the *Server* field. Click *Next*. The installer will connect to the database server and advance to the next step.



Please make sure to select a **SQL Server 2012 instance** in this step.




Figure 5-19 AEDT Setup Wizard – SQL Database



The following error message (Figure 5-20) is displayed under the following circumstances:

- The selected SQL Server instance already has AEDT system databases and sample databases (see Section 5.5 for the list). In this case, manually delete the AEDT system and sample databases and continue with the installation.
- or*
- Side-by-side installation was selected and the same SQL Server instance that is already in use by older version of AEDT was selected. In this case, select a different SQL Server instance.




Figure 5-20 AEDT Setup Wizard – Server in Use Error

12. Click *Install* to start the installation. The installation progress will be displayed.




Figure 5-21 AEDT Setup Wizard – Ready to Install

13. Click *Finish* when installation is complete.




Figure 5-22 AEDT Setup Wizard – Installation Complete

14. A shortcut is created on the Desktop with the name: *AEDT 2d SP2*.

15. In SQL Server Management Studio, check the SQL Server instance where AEDT 2d SP2 databases are installed.

- Verify that the all AEDT system and sample databases were installed.

# Aviation Environmental Design Tool

## Installation Guide: 2d SP2

---

- If any of the system databases are missing, manually restore it using a SQL Server backup file is located in the *DatabaseBackups* folder.  
For example, C:\Program Files\FAA\AEDT 2d SP2\DatabaseBackups

16. AEDT 2d SP2 is ready for use.



AEDT Setup will start Microsoft Distributed Transaction Coordinator (DTC) service if it is not already started on the computer. The DTC provides services designed to ensure successful and complete transactions.

To check DTC settings on your computer:

1. Click the Windows Start button. In the "Search programs and files" text box, enter "services.msc".
2. Find the service, *Distributed Transaction Coordinator*, and double-click on it.
3. If the *Startup type* is set to *Manual*, change it to *Automatic*.
4. Click the *Log On* tab. The "Log on as" should be set to *Network Service*. To change to Network Service, select the "This account" option, then click *Browse*.
5. In the "Enter the object name to select" field, enter "Network Service", then click *OK*.
6. Restart the service.

### 5.3.2 Migrate User-Defined AEDT Study Databases

If there are any user-defined AEDT study databases on a SQL Server 2008 R2 instance, the *Migrate Studies* feature in AEDT 2d application can be used to migrate them to a SQL Server 2012 instance. Follow the instructions in the AEDT User Guide to migrate AEDT study databases.



The migration process does not upgrade the AEDT study version. After migration, upgrade user-defined studies to the most current version, see Section 5.3.3.

### 5.3.3 Upgrade User-Defined AEDT Study Databases

AEDT 2d supports upgrading studies from study database version 1.43.1 up through and including one version prior to the current version. Follow the instructions in the AEDT User Guide to update a user-defined AEDT study database to the latest version.

## 5.4 Optional – Install AEDT Distributed Processing Service

Installing the AEDT Distributed Processing Service is optional. The AEDT Distributed Processing Service is also known as the Taskmaster (TM) Service.

AEDT uses distributed computing to provide the ability to run metric results across a number of remote servers to reduce processing time. A distributed processing system is a collection of computers that communicate through a computer network. Up to fifty remote servers running the Distributed Processing service can be networked to a single AEDT client computer running AEDT application. The AEDT application need only be installed on the AEDT client. On the remote servers, the AEDT Distributed Processing Service need to be installed. If a study references terrain and/or weather files, the necessary files must be placed on all remote servers in the same location specified in the *Definitions* tab on AEDT client. The specified file location must be exactly the same for all remote servers.

Each remote server receives a batch of flight operation information from the AEDT client, processes it, returns the resulting data, and awaits the next batch. The AEDT client assigns batches to the remote servers sequentially, as each remote server becomes available.

There are two installation configurations for distributed processing:

- Standalone configuration: AEDT databases reside on the AEDT client computer (see Figure 5-23 where S1, S2, S3, S4, S5, and S6 represent remote servers), or
- Client – Server configuration: The databases reside on a separate database server (see Figure 5-24, where S1, S2, S3, S4, S5, and S6 represent remote servers). This configuration reduces memory consumption on the AEDT client due to SQL Server processing. The AEDT client relays all necessary information to the remote servers. The remote servers do not communicate directly with the separate database server.




Figure 5-23 Distributed Processing




Figure 5-24 Distributed Processing with Separate Database Server

### 5.4.1 Setup AEDT Client

1. Install the entire AEDT system on the AEDT client, including Microsoft SQL Server, AEDT 2d SP2, and AEDT databases. See sections 5.2 and 5.3.
2. Verify that the AEDT client can run a study successfully. This is an important verification step. If AEDT is not operational on a single machine, AEDT will not operate in distributed processing mode.

### 5.4.2 Setup Taskmaster Servers Running Distributed Processing Service

Repeat the following instructions for each remote server that is being utilized for distributed processing.



AEDT Setup will start Microsoft Distributed Transaction Coordinator (DTC) service if it is not already started on the computer. The DTC provides services designed to ensure successful and complete transactions. The DTC service needs to be running on both client and server(s).

#### *To install AEDT distributed processing service:*

1. To start the installer, double-click the ***Install AEDT 2d SP2 Distributed Processing.exe*** file.
2. If the *User Account Control* dialog box appears, click *Yes*.




Figure 5-25 User Account Control Dialog Box

3. The Setup Wizard for AEDT will open. Click *Next*.




Figure 5-26 AEDT Setup Wizard – Welcome

4. Read the license terms and click *I accept the terms of the license agreement*. Click *Next*.




Figure 5-27 AEDT Setup Wizard – License Agreement

5. Specify the user account that will be used to start the AEDT distributed processing service. You can use an existing user account or create a new user account. Click *Next*.



The user account for the AEDT Distributed Processing Service can be either a local user or a network user.



**The user account for the AEDT Distributed Processing Service must be added to the local *Administrators* group. Please see Step 11 below.**




Figure 5-28 AEDT Setup Wizard – Specify Existing Or New User Account

6. **Existing User Account:** Enter user name, domain, and password of an existing user account. Click *Next*. Verifying the account information may take a while.




Figure 5-29 AEDT Setup Wizard – Specify Existing User Account

7. **Create New User:** Enter user name and password for a new local user account. Click *Next*.




Figure 5-30 AEDT Setup Wizard – Create New User



The password for the local user account must meet the password policy requirements on the local machine. Otherwise, the distributed processing service installation will fail.




Figure 5-31 AEDT Setup Wizard – Unable To Create User Account Error

- Click *Install* to start the installation. The installation progress will be displayed.




Figure 5-32 AEDT Setup Wizard – Ready to Install

- Click *Finish* when installation is complete.




Figure 5-33 AEDT Setup Wizard – Installation Complete

- The AEDT Distributed Processing Service is installed and automatically started. The files to support the service are installed under *C:\Program Files\FAA\AEDT 2d SP2 Distributed Processing*



The Distributed Processing Service logs are written to the *aedt\_TmService.log* under *C:\AEDT\Logs* folder.

# Aviation Environmental Design Tool

## Installation Guide: 2d SP2

11. Add the user account for the AEDT Distributed Processing Service to the local *Administrators* group.  
Otherwise, using distributed processing to run metric results with terrain will not work.
  - a. Click the *Windows Start* button, and enter "*lusrmgr.msc*".
  - b. The *Local Users and Groups* dialog opens.
  - c. Click the *Groups* on the left pane.
  - d. Double-click on the *Administrator* group to open it.
  - e. Add the user account for the AEDT Distributed Processing Service to the *Administrators* group.
  - f. Click OK to save your changes.




Figure 5-34 Local Users and Groups dialog

12. To view the AEDT 2d SP2 Distributed Processing Service:
  - a. Click the *Windows Start* button, and enter "*services.msc*".
  - b. The *Services* dialog opens.
  - c. Find the "AEDT 2d SP2 Distributed Processing Service".




Figure 5-35 Services dialog

## 5.5 Manage AEDT Databases

The following AEDT system databases are installed as part of the complete AEDT installation. After installing AEDT, open the SQL Server Management Studio from the *Start* menu, *All Programs, Microsoft SQL Server 2012, SQL Server Management Studio* and verify that all the AEDT system databases are listed.

- AIRPORT
- FLEET
- STUDY
- STUDY\_DULLES
- STUDY\_IFSET
- STUDY\_INM
- STUDY\_NIRS
- STUDY\_PVD
- STUDY\_WXYZ

### 5.5.1 Verify AEDT System Database Versions

1. Open SQL Server Management Studio from the *Start* menu, *All Programs, Microsoft SQL Server 2012, SQL Server Management Studio*.
2. In the *Connect to Server* dialog box, enter or select the appropriate SQL Server instance name, then click the *Connect* button.
3. From the *File* menu, select *Open, File*.
4. Navigate to *C:\Program Files\FAA\AEDT\Script Files\InstallCheckDBversions.sql* and select *Open*.
5. Click the *Execute* button located on the toolbar.
6. Check the database versions displayed in the *Results* tab.

### 5.5.2 Backup SQL Server Database

1. Open SQL Server Management Studio from the *Start* menu, *All Programs, Microsoft SQL Server 2012, SQL Server Management Studio*.
2. In the *Connect to Server* dialog box, enter or select the appropriate SQL Server instance name then click the *Connect* button.
3. In the *Object Explorer*, select the study database of interest.
4. Right-click on the database, and select *Tasks, Back Up...* to open the *Back Up Database* dialog box.
5. Verify that the *Backup type* is set to *Full*.
6. If an entry has already been added to the *Destination* field, select the entry and click the *Remove* button.
7. Click the *Add* button to open the *Select Backup Destination* dialog box.
8. Click the *...* button and browse to the desired location for storing the backup file.
9. Enter the desired file name in the *File Name* field, including the *.bak* extension. Click *OK*.
10. Click *OK* to close the *Select Backup Destination* dialog box.
11. Click *OK* to back up the database. A confirmation message will be displayed if the backup was successful.




Figure 5-36 Microsoft SQL Server Management Studio – Back Up Database Dialog Box

### 5.5.3 Restore SQL Server Database

The SQL Server backup files (.bak) of the AEDT system databases are located in *C:\Program Files\FAA\AEDT\DatabaseBackups*.

1. Open SQL Server Management Studio from the *Start* menu, *All Programs, Microsoft SQL Server 2012, SQL Server Management Studio*.
2. In the *Connect to Server* dialog box, enter or select the appropriate SQL Server instance name then click the *Connect* button.
3. Right-click on the Databases folder, and select *Tasks, Restore, Database...* to open the *Restore Database* dialog box.
4. Select the *Device* radio button, then click the ... button to open the *Specify backup* devices dialog box.
5. Click the *Add* button. Browse to the location of the previously stored backup file, and click *OK*.
6. Click *OK* to close the *Specify backup* devices dialog box.
7. Select the *Restore* checkbox for the backup file.
8. Select the *Options* page from the left side of the *Restore Database* dialog box.
9. Check the *Overwrite the existing database (WITH REPLACE)* option.
10. Click *OK* to restore the database. A confirmation message will be displayed if the restore was successful.




Figure 5-37 Microsoft SQL Server Management Studio – Restore Database Dialog Box

#### 5.5.4 Delete SQL Server Database

AEDT study databases can be deleted in the SQL Server Management Studio. Exit the AEDT application before deleting an AEDT study database.

1. Open SQL Server Management Studio from the *Start* menu, *All Programs, Microsoft SQL Server 2012, SQL Server Management Studio*.
2. In the *Connect to Server* dialog box, enter or select the appropriate SQL Server instance name then click the *Connect* button.
3. In the *Object Explorer*, select the database of interest.
4. Right-click on the database, and select *Delete* to open the *Delete Object* dialog box.
5. The "Delete backup and restore history information for databases" checkbox is selected by default. Change this setting as desired.
6. Select the "Close existing connections" checkbox.
7. Click *OK* to delete the database and close the dialog box.




Figure 5-38 Microsoft SQL Server Management Studio – Delete Object Dialog Box

## 5.6 Steps to Uninstall AEDT



Before uninstalling AEDT, save desired files from the AEDT data folder (e.g., *C:\AEDT*) and from the study output directories – *C:\AEDT\DATA\[User name]\[Study name]@[SQL Server Instance Name]\Output\_Files* in a different location.

### To uninstall AEDT:

1. Navigate to *Start, Control Panel*, and select *Programs and Features*.
2. Select *AEDT 2d SP2* from the program list and click *Uninstall*.
3. If the *User Account Control* dialog box appears, click *Yes*.




Figure 5-39 User Account Control Dialog Box

4. The Setup Wizard will open. Click *Next* to continue.



Figure 5-40 AEDT Setup Wizard

5. Click the *Remove* button to continue.




Figure 5-41 AEDT Setup Wizard – Remove Installation

6. Click the *Remove* button to uninstall AEDT from the computer.




Figure 5-42 AEDT Setup Wizard – Remove

7. The installer will prompt to delete the Census data files. This refers to the Census data folder used for the Population Exposure Report (default location is C:\AEDT\demographics\_module), and not the ACS data folder used for the Environmental Justice (default location is C:\AEDT\environmentaljustice\_module).
  - Click *Yes* to remove the Census data folder.
  - Click *No* to preserve the Census data folder.



Figure 5-43 AEDT Setup Wizard – Delete Census Data Files Dialog

8. The status bar will display an estimated time to finish removing the program.
9. When the uninstallation is complete, click the *Finish* button to exit the Setup Wizard.
10. Check the following folders and manually delete them as necessary.
  - AEDT installation folder – e.g., C:\Program Files\FAA\AEDT or C:\Program Files\FAA\AEDT 2d SP2
  - AEDT data folder – e.g., C:\AEDT or C:\AEDT 2d SP2
11. Check the SQL Server instance and verify that the AEDT system and sample databases were removed.
  - a. Open SQL Server Management Studio from the *Start* menu, *All Programs, Microsoft SQL Server 2012, SQL Server Management Studio*.
  - b. In the *Connect to Server* dialog box, enter or select the appropriate SQL Server instance name then click the *Connect* button.
  - c. In the *Object Explorer*, expand the Databases folder and confirm that the AEDT system and sample databases are no longer listed. If the AEDT system databases remain, delete them.



If you receive the "Error opening installation log file. Verify that the specified log file location exists and is writable" message when uninstalling AEDT, log off and log in again. This is a known issue with Windows installer.